

# Mosel Language

Quick reference

6.10

QUICK REFERENCE

FICO<sup>®</sup> Xpress Optimization



©2009–2025 Fair Isaac Corporation. All rights reserved. This documentation is the property of Fair Isaac Corporation ("FICO"). Receipt or possession of this documentation does not convey rights to disclose, reproduce, make derivative works, use, or allow others to use it except solely for internal evaluation purposes to determine whether to purchase a license to the software described in this documentation, or as otherwise set forth in a written software license agreement between you and FICO (or a FICO affiliate). Use of this documentation and the software described in it must conform strictly to the foregoing permitted uses, and no other use is permitted.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, please report them to us in writing. Neither FICO nor its affiliates warrant that this documentation is error-free, nor are there any other warranties with respect to the documentation except as may be provided in the license agreement. FICO and its affiliates specifically disclaim any warranties, express or implied, including, but not limited to, non-infringement, merchantability and fitness for a particular purpose. Portions of this documentation and the software described in it may contain copyright of various authors and may be licensed under certain third-party licenses identified in the software, documentation, or both.

In no event shall FICO or its affiliates be liable to any person for direct, indirect, special, incidental, or consequential damages, including lost profits, arising out of the use of this documentation or the software described in it, even if FICO or its affiliates have been advised of the possibility of such damage. FICO and its affiliates have no obligation to provide maintenance, support, updates, enhancements, or modifications except as required to licensed users under a license agreement.

FICO is a registered trademark of Fair Isaac Corporation in the United States and may be a registered trademark of Fair Isaac Corporation in other countries. Other product and company names herein may be trademarks of their respective owners.

Patent(s): [www.fico.com/en/patents](http://www.fico.com/en/patents)

FICO® Xpress Mosel 6.10 (FICO® Xpress 9.7)

Last Revised: 29 July, 2025

## How to Contact the Xpress Team

### Sales and Maintenance

If you need information on other Xpress Optimization products, or you need to discuss maintenance contracts or other sales-related items, contact FICO by:

- Phone: +1 (408) 535-1500 or +44 207 940 8718
- Web: [www.fico.com/optimization](http://www.fico.com/optimization) and use the available contact forms

### Product Support

*Customer Self Service Portal (online support):* [www.fico.com/en/product-support](http://www.fico.com/en/product-support)

*Email:* [Support@fico.com](mailto:Support@fico.com) (Please include 'Xpress' in the subject line)

For the latest news and Xpress software and documentation updates, please visit the Xpress website at <http://www.fico.com/xpress> or subscribe to our mailing list.

# FICO® Xpress Optimization

## Mosel Language

### Quick reference

Release 6.10

29 July, 2025

## Contents

1	Mathematical Programming basics . . . . .	2
1.1	Decision variables . . . . .	2
1.2	Constraints . . . . .	3
1.3	Objective function . . . . .	3
1.4	Optimization . . . . .	3
1.5	Viewing the matrix . . . . .	3
1.6	Viewing the solution . . . . .	3
2	Data handling basics . . . . .	4
2.1	Data types . . . . .	5
2.2	Sums and loops . . . . .	5
2.3	Index sets . . . . .	6
2.4	Reading data in from text files . . . . .	6
2.5	Writing data out to text files . . . . .	7
2.6	User defined data formats . . . . .	8
2.7	Using other data sources . . . . .	8
3	Model building style recommendations . . . . .	9
4	Mosel Language overview . . . . .	10
4.1	Structure of a Mosel model . . . . .	10
4.2	Data structures . . . . .	11
4.3	Selection statements . . . . .	12
4.4	Loops . . . . .	12
4.5	Operators . . . . .	13
4.6	Built in functions and procedures . . . . .	15
4.7	Constraint handling . . . . .	16
4.8	Problem handling . . . . .	17
4.9	Reserved words . . . . .	17
4.10	Annotations . . . . .	18
5	Using the Mosel Command Line . . . . .	18
5.1	Debugger commands . . . . .	19
6	Working with Xpress Workbench . . . . .	20

# 1 Mathematical Programming basics

```

model "Chess 1"
uses "mmpxprs"           ! Use Xpress Optimizer for solving

declarations
  xs, xl: mpvar           ! Decision variables
end-declarations

Time:= 3*xs + 2*xl <= 160 ! Constraint: limit on working hours
Wood:= xs + 3*xl <= 200  ! Constraint: raw mat. availability

xs is_integer; xl is_integer ! Integrality constraints

maximize(5*xs + 20*xl)      ! Objective: maximize total profit

writeln("Solution: ", getobjval) ! Print objective function value

writeln("small: ", getsol(xs))  ! Print solution for xs
writeln("large: ", getsol(xl))  ! and xl

write("Time: ", getact(Time))    ! Constraint activity
writeln(" ", getslack(Time))     ! and slack

end-model

```

## 1.1 Decision variables

```

declarations
  x, b, d: mpvar
  ifmake: array(1..10, 1..20) of mpvar
  y, z: array(1..10) of mpvar
end-declarations

```

mpvar means *mathematical programming variable* or *decision variable*, sometimes also just called *variable*. Decision variables are unknowns: they have no value until the model is run, and the optimizer finds values for the decision variables.

Variables can take values between 0 and infinity by default, other bounds may be specified:

```

x <= 10
y(1) = 25.5
y(2) is_free
z(2,3) >= -50
z(2,3) <= 50

```

Integer programming types are defined as unary constraints on previously declared decision variables

```

b is_binary           ! Single binary variable
forall(p in PRODS, l in LINES)
  ifmake(p,l) is_binary ! An array of binaries
d is_integer          ! An integer variable
d <= 25               ! Upper bound on the variable
x is_partint 10       ! Partial integer (integers up to 10, continuous beyond)
y(3) is_semcont 5     ! Semi-continuous (0 or greater or equal 5)

```

## 1.2 Constraints

Constraint are declared just like decision variables, in LP/MIP problems they have type `linctr` – linear constraint.

```
declarations
  MaxCap: linctr
  Inven: array(1..10) of linctr
end-declarations
```

The “value” of a constraint entity is a linear expression of decision variables, a constraint type ( $\leq$ ,  $\geq$ ,  $=$ ), and a constant term. It is set using an assignment statement:

```
MaxCap := 10*x + 20*y + 30*z <= 100
Ctr(3) := 4*x(1) - 3*x(2) >= 10
Inven(2) := stock(2) = stock(1) + buy(2) - sell(2)
```

## 1.3 Objective function

An objective function is just a constraint with no constraint type.

```
declarations
  MinCost: linctr
end-declarations

MinCost := 10*x(1) + 20*x(2) + 30*x(3) + 40*x(4)
```

## 1.4 Optimization

```
minimize(MinCost)

maximize(MaxProfit)
```

## 1.5 Viewing the matrix

After defining the problem the matrix can be output to a file, to examine off line.

Problem loaded into solver (default: MPS format, use for solver tuning):

```
loadprob(MinCost)
writeprob("explout.mps", "") ! MPS format
writeprob("explout.lp", "1") ! LP format
```

Problem held in Mosel core (default: LP format, constraint oriented file):

```
exportprob("explout", MinCost) ! LP
exportprob(EP_MPS, "explout", MinCost) ! MPS
```

Useful Optimizer control settings:

```
setparam('XPRS_VERBOSE', true)
setparam('XPRS_LOADNAMES', true)
```

## 1.6 Viewing the solution

Always check the solution status of the problem before accessing any solution values.

```

if getprobat=XPRS_OPT then
  writeln('optimal!')
else
  writeln('not optimal!')
  exit(1)
end-if

```

Alternatively, testing all problem states:

```

case getprobat of
  XPRS_OPT: writeln('optimal')
  XPRS_INF: writeln('infeasible')
  XPRS_UNB: writeln('unbounded')
  XPRS_UNF: writeln('unfinished')
else
  writeln('unexpected problem status!')
end-case

```

Accessing the solution values within the model:

```

writeln('Maximum revenue: $', getobjval)
writeln('x(1) = ', getsol(x(1)), ' x(2) = ', x(2).sol)

```

Solution values of constraints: activity value + slack value = RHS

```

MaxCap := 10*x + 20*y <= 30

```

```

Activity value: getsol(10*x + 20*y)
               getact(MaxCap)

```

```

Slack value:   getsol(30 - (10*x + 20*y))
               getslack(MaxCap)

```

Xpress Workbench: assuming that the model runs successfully, the logging pane at the bottom of the workspace reports that the run is complete. If a model has been run through the debugger, you can browse solution values of decision variables and constraints in the *Debugger* tab on the right side of the workspace.

## 2 Data handling basics

```

model "Chess 3"
  uses "mmxprs"

  declarations
    R = 1..2                                ! Index range
    DUR, WOOD, PROFIT: array(R) of real    ! Coefficients
    x: array(R) of mpvar                   ! Array of variables
  end-declarations

  DUR   :: [3, 2]                          ! Initialize data arrays
  WOOD  :: [1, 3]
  PROFIT:: [5, 20]

  sum(i in R) DUR(i)*x(i) <= 160           ! Constraint definition
  sum(i in R) WOOD(i)*x(i) <= 200
  forall(i in R) x(i) is_integer

  maximize(sum(i in R) PROFIT(i)*x(i))
  writeln("Solution: ", getobjval)
end-model

```

## 2.1 Data types

**Constant data**

```

declarations
  N WEEKS = 20
  N DAYS = 7*N WEEKS
  CONV_RATE = 1.425
  DATA_DIR = 'c:\data'
end-declarations

```

### Variable data

**Declaration**

```

declarations
  NPROD: integer
  SCOST: real
  MAXREFVEG: real
  DIR: string
  IF_DEBUG: boolean
  HARD: array(1..5) of real
  COST: array(1..3,1..4) of real
end-declarations

```

**Initialization**

```

NPROD := 20
SCOST := 5
MAXREFVEG := 200.0
DIR := 'c:\data'
IF_DEBUG := true
HARD :: [8.8, 6.1, 2.0, 4.2, 5.0]
COST :: [11, 12, 13, 14,
         21, 22, 23, 24,
         31, 32, 33, 34]

```

## 2.2 Sums and loops

**Summations** Sum up an array of variables in a constraint:

```

MaxCap := sum(p in 1..10) buy(p) <= 100

MaxCap := sum(p in 1..10) (buy(p) + sum(r in 1..5) make(p,r)) <= 100

MaxCap := sum(p in 1..NP, t in 1..NT)
          CAP(p)*buy(p,t) <= MAXCAP

MaxCap := sum(p in 1..NP) (2*CAP(p)*buy(p)/10 +
                          SCAP(p)*sell(p)) <= MAXCAP

```

**Loops** Use a loop to assign an array of constraints:

```

forall(t in 2..NT)
  Inven(t) := bal(t) = bal(t-1) + buy(t) - sell(t)

```

Use do/end-do to group several statements into one loop

```

forall(t in 1..NT) do
  MaxRef(t) := sum(i in 1..NI) use(i,t) <= MAXREF(t)

  Inven(t) := store(t) = store(t-1) + buy(t) - use(t)
end-do

```

Can nest forall statements:

```
forall(t in 1..NT) do
  MaxRef(t) := sum(i in 1..NI) use(i,t) <= MAXREF(t)

  forall(i in 1..NI)
    Inven(i,t) := store(i,t) = store(i,t-1) + buy(i,t) - use(i,t)
end-do
```

Similarly for specification of bounds (a bound is just a simple unnamed constraint):

```
forall(i in 1..NI) do
  forall(t in 1..NT) store(i,t) <= MAXSTORE(t)
  store(i,0) = STORE0
end-do
```

May include **conditions** in sums or loops:

```
forall(c in 1..10 | CAP(c) >= 100.0)
  MaxCap(c) :=
    sum(i in 1..10, j in 1..10 | i <> j)
    TECH(i,j,c) * x(i,j,c) <= MAXTECH(c)
```

## 2.3 Index sets

Explicit statement:

```
declarations
  MaxCap: array(1..10) of lincitr
end-declarations

forall(d in 1..10)
  MaxCap(d) :=
    sum(p in 1..10, m in 1..10)
    TECH(p,m,d) * x(p,m,d) <= MAXTECH(d)
```

Defining named sets:

```
declarations
  PRODUCTS = 1..5
  MATERIALS = {12,487,163}
  DEPOTS = {"Boston","New York","Atlanta"}

  MaxCap: array(DEPOTS) of lincitr
end-declarations

forall(d in DEPOTS)
  MaxCap(d) :=
    sum(p in PRODUCTS, m in MATERIALS)
    TECH(p,m,d) * x(p,m,d) <= MAXTECH(d)
```

Using named sets

- improves the readability of a model
- makes it easier to apply the model to different sized data sets
- makes the model easier to maintain

## 2.4 Reading data in from text files

Read data into COST from cost.dat

```
initializations from 'cost.dat'
COST
end-initializations
```

Data file cost.dat (dense data format)

```
COST : [3.9 0 4.8
        0 7.5 5.5]
```

Data file cost2.dat (sparse data format)

```
COST: [ ("Oil1" 1) 3.9 ("Oil1" 3) 4.8
        ("Oil2" 2) 7.5 ("Oil2" 3) 5.5]
```



- Mosel data format:
- file may include single line comments, marked with '!'
  - format: label, colon, data value(s)
  - for an array, use a single list enclosed in [ ]
  - list may be comma or space separated
  - dense format: the values fill the data table starting at the first position and varying the last index most rapidly
  - sparse format: each data item is preceded by the corresponding index tuple (in brackets)

Specifying the absolute path

```
initializations from 'c:/data/cost.dat'
COST
end-initializations
```

Path relative to current working directory

```
initializations from '../cost.dat'
COST
end-initializations
```

Read several data tables from a single file

```
initializations from 'cost.dat'
SCOST
PCOST
end-initializations
```

Different data label and model object names

```
initializations from 'cost.dat'
COST as 'COST_DETAILS'
end-initializations
```

Read several data arrays with identical index sets from a single table

```
initializations from 'chess.dat'
[DUR,WOOD,PROFIT] as 'ChessData'
end-initializations
```

## 2.5 Writing data out to text files

You can write out values in an analogous way to reading them in

```
initializations to 'cost.dat'
COST
end-initializations
```

To write out the solution values of variables, or other solution values (slack, activity, dual, reduced cost) you must first put the values into a data table

```
declarations
  make_sol: array (ITEMS, TIME) of real
  obj_sol: real
end-declarations

forall (i in ITEMS, t in TIME)
  make_sol(i,t) := getsol(make(i,t))

obj_sol := getobjval

initializations to 'make.dat'
  make_sol
  obj_sol
end-initializations
```

Alternatively, you can use `evaluation` of directly in the `initializations` block

```

initializations to 'make.dat'
  evaluation of
    array(i in ITEMS, t in TIME) getsol(make(i,t)) as 'make_sol'
  evaluation of getobjval as 'obj_sol'
end-initializations

```

## 2.6 User defined data formats

Mosel also provides functions which allow you to read data in from and write data out to text files using any format (see list in Section 4.6).

Reading in free format data

```

declarations
  ii, jj: integer      ! Don't use normal i,j
end-declarations

fopen('cost.dat', F_INPUT)
while(not iseof)
  readln(ii, ',', jj, ',', COST(ii,jj))
fclose(F_INPUT)

```

Writing out data in user format

```

fopen('xsol.dat', F_OUTPUT)
forall(s in SUP, d in DEP)
  writeln(s, ',', d, ',', getsol(x(s,d)))
fclose(F_OUTPUT)

```

## 2.7 Using other data sources

The initializations block can work with many different data sources and formats thanks to the notion of *I/O drivers*.

I/O drivers for physical data files:

- *mmodbc.odbc* for databases with ODBC connector
- *mmsheet.excel* for MS Excel spreadsheets
- *mmsheet.xls* and *mmsheet.xlsx* for generic spreadsheet access, including on non-Windows platforms
- *mmsheet.csv* for CSV format files
- *mmoci.oci* for Oracle databases
- *mmetc.diskdata* for mp-model style data files

Other drivers are available, e.g. for data exchange in memory between models or between a model and the host application.

Change of the data source = change of the I/O driver, no other modifications to your model

```

initializations from "mmsheet.xls:mydat.xls"
  COST as 'CostData'
end-initializations

initializations to "mmodbc.odbc:mydat.mdb"
  SOL as 'SolTable'
end-initializations

```

### 3 Model building style recommendations

- Separation of problem logic and data
  - Typically, the model logic stays constant once developed, with the data changing each run
  - Fix the model and obtain data from their source to avoid editing the model which can create errors, expose intellectual property, and is impractical for industrial size data
- You should aim to build a model with sections in this order
  - *constant data*: declare, initialize
  - *all non-constant objects*: declare
  - *variable data*: initialize / input / calculate
  - *decision variables*: create, specify bounds
  - *constraints*: declare, specify
  - *objective*: declare, specify, optimize
- Use a **naming convention** that distinguishes between different model object types, for example
  - known values (data) using upper case
  - unknown values (variables) using lower case
  - constraints using mixed case
- Variables are *actions* that your model will prescribe
  - Use verbs for the names of variables. This emphasizes that variables represent ‘*what to do*’ decisions
- Try to include ‘min’ or ‘max’ in the name of your objective function; an objective function called ‘OBJ’ is not very helpful when taken out of context!
- Indices are the *objects* that the actions are performed on
  - Use nouns for the names of indices
- Declare all objects in your model (optional unless using compiler option `noimplicit`)
  - Allows the compiler to detect syntax errors more easily
  - Mosel’s guessed declaration doesn’t always work
  - A form of rigour and documentation
  - An opportunity for a descriptive comment
- **Comments** are essential for a well written model
  - Always use a comment to explain what each parameter, data table, variable, and constraint is for when you declare it
  - Add extra comments to explain any complex calculation etc
  - Comments in Mosel:

```

declarations
  make: array(1..NP, 1..NT) of mpvar    ! Amount of p produced in time t
  sell: array(1..NP, 1..NT) of mpvar    ! Amount of p sold in time t
end-declarations

(! And here is a multi-line
comment !) forall(t in 1..NT) ...

```

## 4 Mosel Language overview

### 4.1 Structure of a Mosel model

A Mosel model (text file with extension `.mos`) has the form

```
model model_name

  Compiler directives

  Parameters

  Body

end-model
```

#### Compiler directives

- Options are specified as a *compiler directive*, at the beginning of the model
- Options include `explterm`, which means that each statement must end with a semi-colon, and `noimplicit`, which forces all objects to be declared

```
options explterm
options noimplicit
```

- `uses` statements are also compiler directives

```
uses "mmxprs", "mmodbc"
```

- Can define a version number for your model

```
version 1.0.0
```

#### Run-time parameters

- Scalars (of type `integer`, `real`, `boolean`, or `string`) with a specified default value
- Their value may be reset when executing the model
- Use `initializations from` for inputting structured data (arrays, sets,...)
- At most one `parameters` block per model

#### Model body

- Model statements other than compiler directives and parameters, including any number of
  - declarations
  - `initializations from`/`initializations to`
  - functions and procedures

#### Implicit declaration

- Mosel does *not* require all objects to be declared
- Simple objects can be used without declaring them, if their type is obvious
- Use the `noimplicit` option to force all objects to be declared before using them (see item *Compiler directives* above)

#### Mosel statements

- Can extend over several lines and use spaces
- However, a line break acts as an expression terminator
- To continue an expression, it must be cut after a symbol that implies continuation (e.g. `+`, `-`, `,`, `*`)

## 4.2 Data structures

array, set, list, record and any combinations thereof, e.g.,

```
S: set of list of integer
A: array(range) of set of real
```

### Arrays

*Array*: collection of labeled objects of a given type where the label of an array entry is defined by its index tuple

```
declarations
  A: array(1..5) of real
  B: array(range, set of string) of integer
  x: array(1..10) of mpvar
  C: array(1..5) of real
end-declarations

A:= [4.5, 2.3, 7, 1.5, 10]
A(2):= 1.2
B:= (2..4, ["ABC", "DE", "KLM"]) [15,100,90,60,40,15,10,1,30]
C:= array(i in 1..5) x(i).sol
```

### Sets

*Set*: collection of objects of the same type without establishing an order among them (as opposed to arrays and lists)

Set elements are unique: if the same element is added twice the set still only contains it once.

```
declarations
  S: set of string
  R: range
end-declarations

S:= {"A", "B", "C", "D"}
R:= 1..10
```

### Lists

*List*: collection of objects of the same type

A list may contain the same element several times. The order of the list elements is specified by construction.

```
declarations
  L: list of integer
  M: array(range) of list of string
end-declarations

L:= [1,2,3,4,5]
M:= (2..4) [['A','B','C'], ['D','E'], ['F','G','H','I']]
```

### Records

*Record*: finite collection of objects of any type

Each component of a record is called a *field* and is characterized by its name and its type.

```
declarations
  ARC: array(ARCSET:range) of record
    Source, Sink: string      ! Source and sink of arc
    Cost: real                ! Cost coefficient
  end-record
end-declarations

ARC(1).Source:= "B"
ARC(3).Cost:= 1.5
```

**User types** User types are treated in the same way as the predefined types of the Mosel language. New types are defined in declarations blocks by specifying a type name, followed by =, and the definition of the type.

```
declarations
  myreal = real
  myarray = array(1..10) of myreal
  COST: myarray
end-declarations
```

**Union types** *Union*: container capable of holding an object of one of a predefined set of types. Defined by specifying the set of compatible types or the predefined union type any.

```
declarations
  u: string or real           ! Scalar accepting 'string' or 'real'
  a: any                     ! Scalar accepting any type
  ! Defining a type name for the union of the 4 basic Mosel types:
  basictype = string or integer or real or boolean
  U: array(range) of basictype ! Array of union type 'basictype'
end-declarations
```

## 4.3 Selection statements

```
if ... :           if c=1: writeln('c equals 1')
```

```
if ... end-if     if c=1 then
                  writeln('c equals 1')
                  end-if
```

```
if ... else ... end-if  if c=1 then
                        writeln('c equals 1')
                        else
                          writeln('c does not equal 1')
                        end-if
```

```
if ... elif ... else ... end-if  if c=1 then
                                writeln('c equals 1')
                                elif c>1 then
                                  writeln('c is bigger than 1')
                                else
                                  writeln('c is smaller than 1')
                                end-if
```

```
case ... end-case      case c of
                        1,2 : writeln('c equals 1 or 2')
                        3  : writeln('c equals 3')
                        4..6: do
                            writeln('c is in 4..6')
                            writeln('c is not 1, 2 or 3')
                          end-do
                        else
                          writeln('c is not in 1..6')
                        end-case
```

## 4.4 Loops

```
forall           forall(f in FAC, t in TIME)
                  make(f,t) <= MAXCAP(f,t)

                  forall(t in TIME) do
                    use(t) <= MAXUSE(t)
                    buy(t) <= MAXBUY(t)
                  end-do
```

**with** equivalent to a forall loop stopped after the first iteration

```
with f='F1', t=1 do
  make(f,t) <= MAXCAP(f,t)
end-do
```

**while**

```
i := 1
while (i <= 10) do
  write(' ', i)
  i += 1
end-do
```

**repeat ... until**

```
i := 1
repeat
  write(' ', i)
  i += 1
until i > 10
```

**break, next**

- break jumps out of the current loop
- break *n* jumps out of *n* nested loops (where *n* is a positive integer)
- next jumps to the beginning of the next iteration of the current loop
- use break 'looplabel' and next 'looplabel' with labeled loops:

```
'L1': repeat
  'L2': while (condition1) do
    if condition2 then
      break 'L1'
    end-if
  end-do
until condition3
```

**counter**

- Use the construct as counter to specify a counter variable in a bounded loop (i.e., forall or aggregate operators such as sum). At each iteration, the counter is incremented

```
cnt:=0.0
writeln("Average of odd numbers in 1..10: ",
  (sum(cnt as counter, i in 1..10 | isodd(i)) i) / cnt)
```

## 4.5 Operators

**Assignment operators**

```
i := 10
i += 20      ! Same as i := i + 20
i -= 5       ! Same as i := i - 5
```

**Assignment operators with linear constraints**

```
C := 5*x + 2*y <= 20
D := C + 7*y
```

then D is

```
D := 5*x + 9*y - 20
```

The constraint type is dropped with :=

```
C := 5*x + 2*y <= 20
C += 7*y
```

then C is

```
C := 5*x + 9*y <= 20
```

The constraint type is retained with +=, -=

### Arithmetic operators

standard:	+ - * /
power:	^
int. division/remainder:	mod div
sum:	sum(i in 1..10) ...
product:	prod(i in 1..10) ...
minimum/maximum:	min(i in 1..10) ...
count:	count(i in 1..10   isodd(i))

### Linear and non-linear expressions

Decision variables can be combined into linear or non-linear expressions using the arithmetic operators

- module *mmxprs* only works with linear constraints, so no prod, min, max, ...
- other solver modules, e.g., *mmquad*, *mmnl*, *mmxnlp*, also accept (certain) non-linear expressions

### Logical operators

constants:	true, false
standard:	and, or, not
AND:	and(i in 1..10) ...
OR:	or(i in 1..10) ...
comparison:	<, >, =, <>, <=, >=

### Set operators

constants:	{'A', 'B'}
union:	+
union:	union(i in 1..10) ...
intersection:	*
intersection:	inter(i in 1..10) ...
difference:	-

### Set comparison operators

subset:	Set1 <= Set2
superset:	Set1 >= Set2
equals:	Set1 = Set2
not equals:	Set1 <> Set2
element of:	"Oil5" in Set1
not element of:	"Oil5" not in Set1

### List operators

constants:	[1, 2, 3]
concatenation:	+, sum, union
truncation:	-
equals:	L1 = L2
not equals:	L1 <> L2

### Union and reference operators

testing properties of unions:



```
! u declared as a union type, such as 'any'
writeln(u is array of integer)
writeln(u is not procedure)
```

'reference to' operator:

```
L:= [->cos,->sin,->arctan,->exp]
forall(f in L) writeln(f(0.5))
```

## 4.6 Built in functions and procedures

The following is a list of built in functions and procedures of the Mosel language (excluding modules). Functions return a value; procedures do not.

<b>Dynamic array handling</b>	create	exists	delcell	isdynamic
<b>Freeze (finalize) a dynamic set</b>	finalize			
<b>Rounding functions</b>	ceil	floor	round	abs
<b>Mathematical functions</b>	exp cos isodd	log sin	ln arctan	sqrt
<b>Special real values</b>	isfinite	isinf	isnan	
<b>Random number generator</b>	random	setrandseed		
<b>Minimum/maximum of a list of values</b>	v := minlist(5, 7, 2, 9) w := maxlist(CAP(1), CAP(2))			
<b>Inline "if" function</b>	MAX_INVEN(t) := if(t < MAX_TIME, 1000, 0)  Inven(t) := stock(t) = buy(t) - sell(t) + if(t > 1, stock(t-1), 0)			
<b>Matrix export to file</b>	exportprob   ! Outputs LP/MIP portion handled by ! Mosel core; use solver-specific routines such as ! 'writeprob' of mmxprs for complete matrix output			
<b>File handling</b>	fopen getfid iseof fwrite[_] / fwriteln[_] read / readln	fclose getfname fflush fwrite[_] / fwriteln[_] write[_] / writeln[_]	fselect getreadcnt fskipline	
<b>String handling</b>	strfmt	substr	_	
<b>Access and modify model objects</b>	getcoeff[s] gettype sethidden getnbdim getelt findlast cutfirst reverse	setcoeff settype ishidden getsize getfirst gethead cutlast getreverse	getvars makesos1 setname getlast gettail cuthead splithead	makesos2 setrange  findfirst cutelt cuttail splittail
<b>Access solution values</b>	getobjval getsol getslack	getrcost getact	getdual	

<b>Exit from a model</b>	exit			
<b>Mosel controls</b>	getparam	setparam	localsetparam	restoreparam
<b>Date/time</b>	currentdate	currenttime	timestamp	
<b>Bit value handling</b>	bitflip bitshift	bitneg bittest	bitset bitval	
<b>Handling unions</b>	geteltype	getstruct	gettypeid	isdefined
<b>Miscellaneous</b>	asproc dumpcallstack publish setioerr	assert memoryuse unpublish setmatherr	compare newmuid reset versionnum	datablock   versionstr

### ■ Overloading of subroutines

- Some functions or procedures are *overloaded*: a single subroutine can be called with different types and numbers of arguments

### ■ Additional subroutines are provided by *Mosel library modules*, which extend the basic Mosel language, *e.g.*,

- *mmxprs*: Xpress Optimizer
- *mmodbc*: ODBC data connection
- *mmsystem*: system calls; text handling; date and time types
- *mmjobs*: handling multiple models and (remote) Mosel instances
- *mmsvg*: graphics

⇒ See the ‘Mosel Language Reference Manual’ for full details

### ■ User-defined functions and procedures

- You can also write your own functions and procedures within a Mosel model
- Structure of subroutines is similar to a model (may have declarations blocks)
- User subroutines may define overloaded versions of built in subroutines

⇒ See examples in the ‘Mosel User Guide’ (Chapter *Functions and procedures*)

### ■ Packages

- Additional subroutines may also be provided through *packages* (Mosel libraries written in the Mosel language as opposed to Mosel modules that are implemented in C)

⇒ See the ‘Mosel User Guide’ for further detail (Chapter *Packages*)

## 4.7 Constraint handling

```

Ctrl1:= 2*x + y <= 10      ! Named constraints
Ctrl2:= x is_integer

2*x + y <= 10              ! Anonymous constraints
y >= 5

```

Named constraints can be	accessed:	<code>val:= getact(Ctr)</code> <code>getvars(Ctr, vars)</code>
	hidden:	<code>sethidden(Ctr, true)</code>
	redefined:	<code>Ctr:= x+y &lt;= 10</code> <code>Ctr:= 2*x+5*y &gt;= 5</code>
	modified:	<code>Ctr += 2*x</code> <code>settype(Ctr, CT_UNB)</code>
	deleted (reset):	<code>Ctr:= 0</code>

**Anonymous constraints** are constraints that are specified without assigning them to a `linctr` variable. *Bounds* are (to Mosel) just simple constraints without a name. Anonymous constraints are applied in the optimization problem just like ordinary constraints. The only difference is that it is not possible to refer to them again, either to modify them, or to examine their solution value.

## 4.8 Problem handling

- Mosel can handle several *problems* in a given *model* file. A default problem is associated with every model.
- Built in type `mpproblem` to identify mathematical programming problems
  - The same decision variable (type `mpvar`) may be used in several problems
  - Constraints (type `linctr`) belong to the problem where they are defined
- The statement `with` allows to open a problem (= select the active problem):

```
declarations
  myprob: mpproblem
end-declarations
...
with myprob do
  x+y >= 0
end-do
```

- Modules can define other specific problem types. New problem types can also be defined by combining existing ones, for instance:

```
mypbtyp = mpproblem and somepctype
```

- Problem types support assignment: `P1 := P2`  
and additive assignment: `P1 += P2`

## 4.9 Reserved words

The following words are reserved in Mosel. The upper case versions are also reserved (*i.e.* AND and and are keywords but not And). Do not use them in a model except with their built-in meaning.

```
a:  and  any  array  as
b:  boolean break
c:  case constant count counter
d:  declarations div do dynamic
e:  elif else end evaluation
f:  false forall forward from function
h:  hashmap
i:  if imports in include initialisations initializations
```

```

integer  inter  is  is_binary  is_continuous  is_free
is_integer  is_partint  is_semcont  is_semint  is_sos1  is_sos2
linctr  list
max  min  mod  model  mpproblem  mpvar
namespace  next  not  nsgroup  nssearch
of  options  or
package  parameters  procedure  public  prod
range  real  record  repeat  requirements  return
set  shared  string  sum
then  to  true
union  until  uses
version
while  with

```

## 4.10 Annotations

- *Annotations* are meta data in a Mosel source file that are stored in the resulting BIM file after compilation; no impact on the model itself (treated like comments); either global or associated with public globally declared objects (including subroutines).
- Single-line annotations start with '`!@`' and a name; blocks are surrounded by '`!@`' and '`!)`'
- `!@doc.descr` denotes the annotation marker `descr` within category `doc` (predefined category names are `mc` and `doc`, user-defined names can also be employed)

```

(!@doc.  Enter category 'doc' (this text is ignored)
 @ descr This is the value of 'doc.descr'
 @.      Jump back to root (this text is ignored)
@mynote  Contents of 'mynote' (full name: '.mynote')
@.anote  Complete form of an annotation in default category
!)
```

- *Declaring annotations* (via the `mc.def` compiler annotation): optional; enables the compiler to check the validity of the definitions and reject non-compliant ones

```

! Defining an alias that redirects onto 2 different annotations:
!@mc.def descr alias doc.descr om.descr

```

- *mosel doc* tool: generates an XML model documentation that is processed into HTML pages

1. Compile source model file with option `-D`

```
mosel comp -D mymodel.mos
```

2. Run program `mosel doc`

```

mosel doc mymodel           Generates HTML and XML
mosel doc -o mydir -html mymodel  HTML only, specifying output directory
mosel doc -f -xml mymodel      XML only, forcing output overwrite

```

See 'Mosel Language Reference', section *Documenting models using annotations* for a list of the `doc` annotations

## 5 Using the Mosel Command Line

The Mosel Command Line is supported on all platforms that Mosel can be run on.

**Standard sequence for model execution** from the command line:

```
mosel exec mymodel.mos      Execute (=compile/load/run) model 'mymodel.mos'
mosel mymodel               Short form (works with 'mymodel.mos' or 'mymodel.bim')
```

Some useful commands (see 'Mosel Language Reference manual' for the full list):

<i>Command line help text:</i>	<code>mosel -h</code>
<i>Mosel version:</i>	<code>mosel -V</code>
<i>Display functionality:</i>	<code>mosel exam[ine] [-cspthirvaum]</code>
<i>Execute a model file:</i>	<code>mosel exec[ute]</code>
<i>Compile a model file:</i>	<code>mosel comp[ile] mymodel.mos</code>
<i>Load and run a BIM file:</i>	<code>mosel run mymodel.bim</code>
<i>Start the debugger:</i>	<code>mosel debug mymodel.mos</code>
<i>Run the profiler:</i>	<code>mosel prof[ile] mymodel.mos</code>
<i>Perform a code coverage run:</i>	<code>mosel cover[age] mymodel.mos</code>
<i>List available modules/packages:</i>	<code>mosel lslib</code>

#### Examples:

```
mosel comp mymodel.mos -o mybim.bim  Compile to a specified BIM file name/location
mosel prof mymodel.mos               Perform a profiler run (output in 'mymodel.mos.prof')
mosel exam -h                       Display Mosel version info and paths
mosel exam -a mybim.bim              Display annotations of a model or package
mosel exam -ps mmxprs                Display parameters and subroutines of module 'mmxprs'
```

#### Setting model runtime parameters:

```
mosel exec mymodel NT=5 DATAFILE="mynewdata.dat"  Source in mymodel.mos
mosel run mymodel NT=5 DATAFILE="mynewdata.dat"  Loads mymodel.bim
mosel mymodel NT=5 DATAFILE="mynewdata.dat"      With mymodel.mos or mymodel.bim
```

## 5.1 Debugger commands

<i>Breakpoints:</i>	<code>break delete bcond[ition] breakpoints breaksub</code>
<i>Model execution:</i>	<code>cont next step finish model</code>
<i>Output:</i>	<code>display undisplay list print info exportprob lsattr lslibs lslocal lsmods lssymb</code>
<i>Stack access:</i>	<code>up down where</code>
<i>Interpreter options:</i>	<code>option</code>
<i>Termination:</i>	<code>quit</code>

#### Example: Simple debugging sequence

mosel debug debugexpl.mos	<i>Start Mosel debugger</i>
break 20	<i>Set breakpoint at line 20</i>
cont	<i>Execute up to the breakpoint</i>
print D	<i>Print out symbol 'D'</i>
cont	<i>Continue model execution</i>
info Arr	<i>Information about model object 'Arr' (e.g. size)</i>
lsmods	<i>Display model info (e.g. memory usage)</i>
quit	<i>Quit the debugger</i>

### Example: Debugging a submodel

mosel debug debugmain.mos	<i>Start Mosel debugger on main model</i>
breaksub 1	<i>Stop at start of submodels</i>
cont	<i>Execute up to the breakpoint</i>
break 25 debugsub.mos	<i>Set breakpoint in the submodel</i>
display SNumbers	<i>Display watch on object 'SNumbers'</i>
cont	<i>Execute up to the breakpoint</i>
break 31 debugsub.mos	<i>Another submodel breakpoint</i>
bcond 2-2 SNumbers.size < 10	<i>Condition on 2nd submodel breakpoint</i>
cont	<i>Execute up to the breakpoint 2-2</i>
quit	<i>Quit the debugger</i>

## 6 Working with Xpress Workbench

Xpress Workbench is an integrated development environment (IDE) for Mosel models and Xpress Insight applications.

### Workbench panes

Model editor (central window), project directory navigation and command history (left), model output and execution log information (bottom), debugging, deployment and collaboration information (right).



Workspace preferences (settings).



Toggle full-screen view for logging pane.

Use menu *Window>>Presets>>Full IDE* to restore original window layout.

### Editor

Code folding and breakpoint markers appear in the grey area immediately left to the text.



Open a new file/tab



Subdivide and re-arrange panes in the editor window



Code folding for blocks of Mosel statements



Unfold folded code



Line position markers during debugging

### Model execution

The name of the model is selected in the box next to these buttons, it may be different from the model(s) opened in the editor.



Compile a model (Ctrl-B).



Execute (compile/load/run) a model (Ctrl-F5).



Execute (compile/load/run) a model in debug mode (F5).



Open *Compiler Options* or *Run Dialog* windows.








Alternatively, use menu *Run* to compile or run a model.

## Debugger







Breakpoints are set by clicking onto the gray area (left to the line number if it is displayed) preceding each row in the editor window.

 Delete breakpoint/deactivated breakpoint.

Navigating in the debugger (select *Debugger* tab on right border):

 Activate/deactivate all breakpoints.  
 Start/stop the debugger.  
 Resume/suspend model execution (F8).  
 Step over an expression (F10).  
 Step into an expression (F11).  
 Step out of an expression (Shift-F11).  
 Don't pause on exceptions.

## Deployment to Xpress Insight

 Publish selected model to Insight (Ctrl-Alt-P).  
 Build an Insight app archive (Ctrl-Shift-A).  
 Debug a scenario.  
 Edit Tableau workbooks (Ctrl-Alt-T).  
 Refresh Insight scenario tree.  
 Xpress Insight settings.